

Moneybookers integration with



Agenda

- 1 **Information of Moneybookers**
- 2 Payment process for customers
- 3 The most frequently used payment methods



About the official Moneybookers payment module for



Moneybookers is an all in one payments solution that enables a merchant to accept debit and credit card payments, bank transfers and the largest range of local payments directly on your website.

- Widest network of international and local payment options in the world
- One interface including payments, banking and marketing
- Direct payments without the need for prior registration
- Moneybookers stands for a highly converting payment gateway that turns payment processing into a simple, fast and customer friendly operation
- Highly competitive rates

First of all you need to download and install the module which can be found here:

www.moneybookers.com/partners/drupal/moduledrupal.zip



Information of Moneybookers

Please note the following points before starting the installation of Moneybookers:

1. Create Moneybookers account:

If you have not already created a Moneybookers account, please sign up here:

<http://www.moneybookers.com/partners/drupal/>

2. Wait for your activation. You will be notified by e-mail.

3. Choose a secret word in your Moneybookers account under “Merchant Tools” and then click on “confirm”. Note: this option is only available after activation. The secret word is for additional security to protect your transactions.

4. Start Moneybookers installation in your Drupal software.



Moneybookers settings

Home > Administer > Store administration > Configuration

Payment settings Overview Edit

Payment settings:

- Payment tracking is enabled.
- Payments can be deleted by users with permission.
- Log payments are being entered to and deleted from the order log.
- Default payment details message is:
Continue with checkout to complete payment.

Payment methods:

- Moneybookers eNETS is enabled for checkout.
- Moneybookers iDeal is enabled for checkout.
- Moneybookers Nordea Solo is enabled for checkout.
- Moneybookers Poste Pay is enabled for checkout.
- Moneybookers Przelewy24 is enabled for checkout.
- Moneybookers Poli is enabled for checkout.
- Moneybookers Nordea Solo is enabled for checkout.
- Moneybookers Carte Bleue is enabled for checkout.
- Moneybookers Laser is enabled for checkout.
- Moneybookers Solo is enabled for checkout.
- Moneybookers CartaSi is enabled for checkout.
- Moneybookers Visa Electron is enabled for checkout.

Home > Administer > Store administration > Configuration > Payment settings

Payment settings Overview Edit

Payment settings Payment methods Payment gateways

Payment methods

The settings forms below are for the payment methods defined by enabled modules. Click a name to expand its options and adjust the settings accordingly. Methods are listed in order of appearance on the checkout screen, determined by the list position setting (current value shown in parentheses).

Enabled	Payment method	List position	Default gateway
<input checked="" type="checkbox"/>	Moneybookers eNETS	-7	-
<input checked="" type="checkbox"/>	Moneybookers iDeal	-7	-
<input checked="" type="checkbox"/>	Moneybookers Nordea Solo	-7	-
<input checked="" type="checkbox"/>	Moneybookers Poste Pay	-6	-
<input checked="" type="checkbox"/>	Moneybookers Przelewy24	-6	-
<input checked="" type="checkbox"/>	Moneybookers Poli	-6	-
<input checked="" type="checkbox"/>	Moneybookers Nordea Solo	-6	-
<input checked="" type="checkbox"/>	Moneybookers Carte Bleue	-5	-
<input checked="" type="checkbox"/>	Moneybookers Laser	-5	-
<input checked="" type="checkbox"/>	Moneybookers Solo	-5	-
<input checked="" type="checkbox"/>	Moneybookers Visa Electron	-5	-
<input type="checkbox"/>	Moneybookers CartaSi	-5	-
<input checked="" type="checkbox"/>	Moneybookers Euro6000	-5	-
<input checked="" type="checkbox"/>	Moneybookers Maestro	-5	-

Save configuration

1. In the “Payment Methods” section select the payment method which you want to offer in you store, for example “Moneybookers Visa Electron”
2. Choose the order in which selected payment method will appear in checkout
2. Click on “Save configuration”

Each additional payment option will bring you more customers. With Moneybookers you will have no additional cost, regardless of whether you integrate one or more payment options offered via Moneybookers.



Moneybookers settings

Home > Administer > Store administration > Configuration > Payment settings

Payment settings Overview Edit

Payment settings Payment methods Payment gateways

Moneybookers settings

To have access to the international payment of Moneybookers please register [here](#) for a free account, if you don't have one yet.

1. Email address of shop account:

Validate Email

Moneybookers customer ID:
5185770
Your Moneybookers customer ID number.

Correspondence language with Moneybookers:

Which language would you prefer corresponding with Moneybookers

2. Activate Moneybookers Quick Checkout

Moneybookers Quick Checkout enables you to take direct payments from credit cards, debit cards and over 60 other local payment options in over 200 countries as well as the Moneybookers eWallet.

If you have not set up an account, click here

1. Enter your Moneybookers e-mail address and press “Validate Email”
2. Activate Moneybookers Quick Checkout

If you have not requested to become a merchant yet, please activate Moneybookers Quick Checkout to get the necessary tools. A request is sent automatically to Moneybookers. Moneybookers checks your shop and activates it within 2 working days. You will be informed of the activation by e-mail.



Moneybookers settings: Moneybookers secret word

After you have received confirmation of the activation, log into your account at www.moneybookers.com. A new area called "Merchant tools" is now activated. Select a secret word here that locks the payments.

1. Select "Merchant tools"
2. Select a secret word. This should be:
 - max. 10 characters
 - only small letters and numbers and no special characters
 - different to your password
3. Enter your secret word in the Drupal administration

moneybookers.com
and money moves

SEND MONEY SHOPPING SERVICES MY ACCOUNT

Email: demo@moneybookers.com
Customer ID: 5185770
Balance: 487.11 EUR

• Summary
• History
• Profile
• View limit
• Change password
• Email support
• Merchant tools

WELCOME MR. PAUL PAYER!

ACCOUNT SUMMARY

Balance	487.11 EUR
Last transaction	+0.90 EUR
Last successful login	20 Nov 2008, 18:16 (CET)

ACCOUNT STATUS

Moneybookers Account	Personal Account
Address	[Verify]
Credit/debit card	[Add]
Bank account	[Add]

ACCOUNT LIMITS

Your credit/debit card deposit limit	0.00 EUR
Remaining	0.00 EUR
Your outgoing transaction limit	11000.00 EUR [?]
Remaining	11000.00 EUR [Increase]

• Summary
• History
• Profile
• View limit
• Change password
• Email support
• Merchant tools

MERCHANT TOOLS

Mr. Paul Payer

PLEASE INSERT YOUR SECRET WORD BELOW:


Secret Word: *****

Confirm Secret Word: *****



Moneybookers settings

1.



A screenshot of a dropdown menu with the text "Moneybookers eWallet settings" highlighted by an orange box.

2.



A screenshot of a form for secret word verification. It includes a text input field for the secret word, a "Validate Secret Word" button, and a "Support:" section with contact information for Moneybookers.

3.



A screenshot of the "Payment settings" page. It shows a breadcrumb trail, a "Save configuration" button, and a message indicating that the secret word was successfully checked and the configuration can be saved.

1. e-Wallet must be activated first in the payment methods section, so please select Moneybookers e-Wallet settings
2. Enter your Secret word and click on “Validate Secret word”
3. Once the secret word has been validated you can then select “Save configuration”



Agenda

- 1 Information of Moneybookers
- 2 **Payment process for customers**
- 3 The most frequently used payment methods



Payment procedure for customers: Product selection

MB T-shirt
Fri, 08/14/2009 - 13:39 — Anonymous

Moneybookers T-shirt \$12.00

\$12.00

1.

Shopping cart

MB T-shirt added to your shopping cart.

Remove	Products	Qty.	Total
<input type="checkbox"/>	MB T-shirt	<input type="text" value="1"/>	\$12.00
			Subtotal: \$12.00

[Continue shopping](#) **2.**

1. Select the product you want and click on “Add to Cart”

2. Click “Checkout” to continue



Payment procedure for customers: personal data

E-mail address: *

▼ **Delivery information**

Enter your delivery address and information here.

***First name:**

***Last name:**

Company:

***Street address:**

***City:**

***Country:** United States ▼

***State/Province:** Please select ▼

***Postal code:**

Phone number:

▼ **Billing information**

Enter your billing address and information here.

My billing information is the same as my delivery information.

***First name:**

***Last name:**

Company:

***Street address:**


***City:**

***Country:** United States ▼

***State/Province:** Please select ▼

***Postal code:**

Phone number:

 Please enter your personal data



Payment procedure for customers: Close order

1. Choose one of the Moneybookers Payment Methods
2. Then select “Review order”
3. Complete payment details and submit order

1.

The screenshot shows a payment method selection interface. At the top, there is a dropdown menu labeled "Payment method" with a downward arrow. Below it, the text "Select a payment method from the following options." is displayed. A dashed box contains an "Order total preview" section with the following details:

Subtotal:	\$12.00
Order total:	\$12.00

Below the preview, the section "Payment method: *" is shown with several radio button options, each accompanied by a logo:

- Payment via credit card: (with a credit card logo)
- Payment via Direct Debit:
- Payment via GiroPay: (with a giro pay logo)
- Payment via Moneybookers eWallet:
- Payment via Sofortueberweisung: (with a sofort logo)
- Payment via EPS: (with an eps logo)

At the bottom of the interface, there are three buttons: "Cancel", "Review order", and "Submit order". The "Review order" button is highlighted with an orange box and labeled "2.". The "Submit order" button is highlighted with an orange box and labeled "3.". A large orange bracket on the left side of the interface spans from the "Payment method" dropdown down to the "Review order" button, with the number "1." next to it, indicating that this entire section corresponds to the first step of the procedure.

2.


3.




Payment procedure for customers: Payment via Moneybookers

To pay for the seller's article, enter your data in the Moneybookers' SSL-protected payment mask and click on the "CONFIRM AND PAY" button

Payment to **demo@moneybookers.com**
TOTAL PAYABLE : **16.00 EUR**
[+ More information](#)


Pay with 


First name*:
Last name*:
Card type*: DELTA / VISA DEBIT
Card number*:
Expiry date*: / CVC Code: 

By clicking the button below you confirm to have accepted the Moneybookers [Terms and Conditions](#) and [Privacy Policy](#)


CONFIRM AND PAY

* required to be filled out

Select language: 

powered by  moneybookers.com
and money moves

[I already have a Moneybookers account](#)

 VERIFY >



Agenda

- 1 Information of Moneybookers
- 2 Payment process for customers
- 3 The most frequently used payment methods**



Moneybookers : Widest support of local payment options



Moneybookers contact



Moneybookers Merchant Service

E-Mail: ecommerce@moneybookers.com

Telephone : +44 870 383 0762

